## o netelip

### Manual de configuración softphone 3CX para PC



Este manual explica como configurar el softphone para ordenador 3CXphone y conectarlo al servicio de Netelip para realizar y recibir llamadas.

#### Paso 1

Registrate en http://www.netelip.com/.

Al registrarte recibirás un correo electrónico con los datos de tu cuenta SIP (nombre de usuario, contraseña y dominio de nuestro servidor de voz) o tu extensión vPBX.

#### Paso 2

Has de descargar la aplicación gratuita 3CX para tu ordenador desde el siguiente enlace http://www.3cx.es/voip-telefono/index.html. Guarda y ejecuta el archivo para poder instalarlo en tu PC.

#### Paso 3

Una vez instalado, ábrelo y pincha en la parte superior para entrar en el apartado de "cuentas" y crear una nueva para Netelip pinchando en "New".



Account	S					
Accounts Manage SIP accounts						
Active	Name	Domain	Caller ID		New D	
	Netelip_3CX	0019293576102@v	Administrador		Edit	
					Remove	
					Soft keys	
				ОК	Cancel	

# onetelip

Account name:	New account
Account name:	New account
Caller ID:	Administrador
Iredentials	
Enter your SIP account credenti	als
Extension:	
ID:	
Password:	
4y location	
Specify the IP of your PBX/SIP s	erver
I am in the office - local IP	of F
· · · · · · · · · · · · · · · · · · ·	al ID
Use 3CX Tunnel	
Use 3CX Tunnel Eliminates firewall configuration. Windows	Requires 3CX Phone System for
Use 3CX Tunnel Eliminates firewall configuration. Windows Local IP of remote PBX;	Requires 3CX Phone System for
Use 3CX Tunnel Eliminates firewall configuration. Windows Local IP of remote PBX: Tunnel password:	Requires 3CX Phone System for
Use 3CX Tunnel Eliminates firewall configuration. Windows Local IP. of remote PBX: Tunnel password: Use Outbound Proxy server	Requires 3CX Phone System for           ***         Port:         5090
Use 3CX Tunnel Eliminates firewall configuration. Windows Local IP of remote PBX: Tunnel password: Use Outbound Proxy server Required by some VoIP Provider	Requires 3CX Phone System for           ***         Port:         5090           5. Specify IP or name.         5000         5000
Use 3CX Tunnel Eliminates firewall configuration. Windows Local IP of remote PBX: Tunnel password: Use Outbound Proxy server Required by some VoIP Provider	Requires 3CX Phone System for           ****         Port:         5090           s. Specify IP or name.         5000         5000
Use 3CX Tunnel Eliminates firewall configuration. Windows Local IP of remote PBX: Tunnel password: Use Outbound Proxy server Required by some VoIP Provider	Requires 3CX Phone System for
Use 3CX Tunnel Eliminates firewall configuration. Windows Local IP of remote PBX: Tunnel password: Use Outbound Proxy server Required by some VoIP Provider Perform provisioning from foll	Requires 3CX Phone System for          ***       Port:       5090         s. Specify IP or name.       Summer System for name.
Use 3CX Tunnel Eliminates firewall configuration. Windows Local IP of remote PBX: Tunnel password: Use Outbound Proxy server Required by some VoIP Provider Perform provisioning from foll http://	Requires 3CX Phone System for          ****       Port:       5090         s. Specify IP or name.       Specify IP or name.

Los datos que han de insertarse para crear el perfil de Netelip en la aplicación 3CX son los siguientes:

**Account name:** Introduce el nombre que quieras a la cuenta

*Caller ID:* Introduce un identificador para la cuenta

Ahora en el apartado de "Credentials", has de insertar los datos de configuración SIP que recibiste por e-mail tras registrarte en www. netelip.com

*Extension:* Introduce tu usuario SIP *ID:* Introduce tu usuario SIP de nuevo *Password:* Introduce tu contraseña SIP

En el apartado de "My location", marca:

*I am in the office – Local IP* e introduce el servidor sip de tu cuenta Netelip (sip.netelip. com) o el servidor de tu extensión en caso que estés configurando tu vPBX (vpbx.netelip.com)

Acepta los cambios haciendo clic en OK. Tu aplicación 3CX deberá mostrar que está registrada indicando **On hook.** 



Account settings							
Account name:	Netelip 3CX						
Caller ID:							
Credentials							
Enter your SIP account credentials							
Extension:	00192935761						
ID:	00192935761						
Password:	*****						
My location							
Specify the IP of your PBX/SIP server							
I am in the office - local IP	vpbx.netelip.com of PBX						
$ \mathbb{C}$ I am out of the office - external IP	of PBX						
Use 3CX Tunnel							
Eliminates firewall configuration. Requires 3CX Phone System for Windows							
Local IP of remote PBX: Vpb	netelip.com						
Tunnel password:	Port; 5090						
Use Outbound Proxy server							
Required by some VoIP Providers. Specify IP or name.							
Perform provisioning from following URL:							
http://							
Advanced settings	OK Cancel						

Ahora ya puedes realizar y recibir llamadas con el servicio de Netelip.